HOW TO PRINT AN <u>A5 SPIRAL BOUND MINISTRY BOOK</u> FROM THE <u>WEBSITE</u>

The instructions are for **Adobe Acrobat Reader** but can be adapted for other PDF Readers

1. Click the A5 version of the book Cover or Interior and it will open as a PDF file in your browser		
2. Right click anywhere on the book on the screen and click ' Print ' on the menu		
Customise the Print Window	Print 64 sheets of paper	
 More settings – click arrow to produce this extended view 	Pages All 🔹	
	Copies 1	
4. Color – select 'Color' for the Cover and 'Black and white' for the Interior	Colour	
from the dropdown menu	More settings	
5. Paper size – select 'A4	Paper size A4 🔻	
	Pages per sheet 1	
6. Pages per sheet – select 1	Scale Customised	
7. Scale – select 'Customised'	144	
8. Type 144	Two-sided Print on both sides Flip on short edge	
9. Scroll down and click 'Print using system dialogue'	Print using system dialogue (Ctrl+Shift+P)	
Customise the System Dialogue Print Window	Print X General	
10. Select the number of copies you want	Select Printer Select Printer	
11. Select 'All'	Status: Ready Preferences Location: Find Printer	
12. Click 'Preferences'	Page Range All Selection Current Page Pages: 1-12 Enter page numbers and/or page ranges separated by commas. For example, 1,5-12	
	Print Cancel Apply	

	D
<u>Customise the Printing Preferences – Layout Tab</u>	Layout Paper/Quality
	Orientation:
13. Select 'Portrait'	Portrait ~
14. Select 'Flip on Short Edge'	Print on Both Sides:
15. Select 'Front to Back'	Front to Back Page Format
16. Pages per sheet – select 1	Pages per Sheet
17. Select 'Booklet'	Draw Borders
18. Untick 'Draw Borders'	Advanced
19. Click the Paper/Quality tab	OK Cancel
Customise the Printing Preferences –	Printing Preferences ×
Paper/Quality Tab	Layout Paper/Quality
Paper/Quality Tab	Tray Selection
	Paper Source: Printer Auto Select
	Paper Size:
20 Coloct (Dect' or (Nerrol' for the Cover	Media: Plain Paper ~
20. Select 'Best' or 'Normal' for the Cover	Quality Settings
Select 'Normal' or 'Draft' for the Interior	O Best Normal O Draft Custom
21. Click OK	Advanced OK Cancel
22. For the Cover use card (160 g/m ² works well) For the Interior use paper	
Apply the Preferences and Print	₿ Print X
Apply the references and rint	General
23. Click 'Apply'	Select Printer The POffice Pro 8600 (Network) Send To OneNote 2016 Microsoft XPS Document Writer Status: Ready Location: Comment Find Printer.
24. Click 'Print'	Page Range All Selection Current Page Pages: 12 Entropic numbers and/or page ranges separated by commas. For example, 1,5-12 Print Cancel Apply
25. Cut the pages in half using a guillotine for a clean cut Put the 2 piles of Interior pages together. Check orientation is correct and pages in the right order Put the 2 Cover pages either side of the interior pages	
26. Place an A5 Clear PVC Report Cover at each end of the book	
27. Use a binding machine to bind the pages into a book Cut the binding combs down to size and you have your book	